

# Binding to Target Application Error After Upgrading QA Wizard Pro

## Problem

The following error is returned when recording or running scripts after upgrading QA Wizard Pro:

'Error binding to the target application: [510]'

## Cause

QA Wizard Pro injects code into target applications during recording and playback, which creates a lock on some QA Wizard Pro libraries as long as the tested applications are open. The locked libraries cannot be updated during the upgrade.

## Solution

1. Close QA Wizard Pro, QAWizardRemote.exe, the QA Wizard Pro status tool, and any open browsers or applications used by QA Wizard Pro.
2. Perform the upgrade again.

---

Article ID: 787

Last updated: 07 Jun, 2017

Revision: 2

QA Wizard Pro -> Binding to Target Application Error After Upgrading QA Wizard Pro

<http://www.seapine.com/knowledgebase/index.php?View=entry&EntryID=787>