

Binding to Target Application Error After Upgrading QA Wizard Pro

Problem

The following error is returned when recording or running scripts after upgrading QA Wizard Pro:

'Error binding to the target application: [510]'

Cause

QA Wizard Pro injects code into target applications during recording and playback, which creates a lock on some QA Wizard Pro libraries as long as the tested applications are open. The locked libraries cannot be updated during the upgrade.

Solution

1. Close QA Wizard Pro, QAWizardRemote.exe, the QA Wizard Pro status tool, and any open browsers or applications used by QA Wizard Pro.
2. Perform the upgrade again.

Article ID: 787

Last updated: 07 Jun, 2017

Revision: 2

QA Wizard Pro -> Binding to Target Application Error After Upgrading QA Wizard Pro

<http://www.seapine.com/knowledgebase/index.php?View=entry&EntryID=787>