

# Controls Duplicated in the QA Wizard Pro Application Repository

## Problem

An existing control is duplicated in the QA Wizard Pro application repository after recording.

## Cause

QA Wizard Pro does not uniquely recognize the existing control in the repository based on the search criteria used to locate it.

## Solution

[Merge the duplicate controls](#). After merging, make sure to [select appropriate search criteria for the control](#) so it is unique in the repository.

You can also use the following options when [reviewing and saving repository changes](#) to help reduce adding duplicate controls to the repository.

- Make sure the 'Smart matching' option is selected in the Repository Changes dialog box after recording. Smart matching lets QA Wizard Pro automatically modify search criteria to differentiate controls.
- Select the 'Only add used controls to the repository' option in the Repository Changes dialog box to only add controls you interacted with.

---

Article ID: 791

Last updated: 26 Jun, 2017

Revision: 4

QA Wizard Pro -> Controls Duplicated in the QA Wizard Pro Application Repository

<http://www.seapine.com/knowledgebase/index.php?View=entry&EntryID=791>